



一、IE web5.0 .....	2
二、IE web6.0 .....	4

# 一、IE web5.0


1、 Configuration—Storage Management—Disk Management, click “Initialize Disk”;





2、 Click “Confirm”




3、 Click “Confirm”



4、 wait ,until it shows “Formating complete”, camera will reboot;




5、 Set the Record Policy




6. Click Save

## 二、IE web6.0

1、 Configuration—Storage—SD/USB List, click “Initialize Disk”;



2、 click “ok”



3、 wait until see Operation Succeeded;

Device	Total Space	Used Space	Free Space	State	Usage
<input checked="" type="checkbox"/> SD1	13.50GB	512MB	13.00GB	Using	Record

Initialize Disk

here you will see

Operation Succeeded

#### 4、 Configuration—Storage—Schedule Recording;

**Tiandy** Live View Playback Log **Configuration**

Basic Set  
Video  
Network  
Event  
VCA  
Storage  
**Schedule Recording**  
Storage Policy  
SD/USB List  
NFS  
FTP  
System

Recording Location  SD/USB  NFS  FTP

Record Status Schedule

Schedule

Schedule Monday

00:00 ~ 23:59  
 00:00 ~ 00:00  
 00:00 ~ 00:00  
 00:00 ~ 00:00

Copy To  All

Sun  Mon  Tue  Wed  Thu  Fri  Sat

ANR OFF

Note: Offline recording will follow timing recording rule.

5. Click Save.